

Axon + Flock Safety Integrations

If your agency has both Axon Fleet 3 mobile ALPR and Flock Safety Fixed ALPR, you have the option to establish an API connection between Axon Evidence and Flock Safety which will enable you to perform plate searches across both Axon mobile ALPR records and Flock Safety fixed ALPR records in a single user interface in the Flock Safety Dashboard. The API integration also allows you to upload Flock Safety records to Axon Evidence as a piece of evidence. For information on setting up the integration, see [Flock Safety – Fleet 3](#).

View Axon Fleet 3 images in Flock Safety search


Agencies can expand their search capabilities within Flock by unlocking Axon's Fleet 3 images alongside Flock's results, and using Flock's Location filters to help narrow down results to obtain objective evidence faster.

Steps are provided below to search by location or device. Users can only search by Location *or* Device, not both.


Search by Location

Note: A location-based search is currently the only way to retrieve both Axon Fleet 3 and Flock results in your Search.


1. On the Flock [Search page](#), choose the down arrow next to **Select by**, and then select **Location**.




2. Select **Open Map**.



3. In the map Location search bar, **enter a location** (Address, City, etc.) you want to investigate.
 4. Select the polygon button or **Set Location**, draw a shape around the desired search area, and then choose **Save Selection**.
- Note:** Switching between cameras or location will reset the previous selection.



5. Use the date and time fields to set your desired time frame, enter a **Search Reason**, and then select **Search Now**. The search will yield all Flock and Axon generated results within the selected location and radius.



6. Browse the results generated within their specified location. Vehicle and license plate characteristics can be filtered and applied to both Axon and Flock records simultaneously to simplify record keeping and keep all evidence uniform.

Axon Fleet 3 Camera System Quick Start Guide (continued)

The screenshot shows the Axon Search interface. The top navigation bar includes 'Search', 'Alerts', 'Map', 'Devices', 'Sharing', 'Insights', and 'Admin'. The left sidebar contains filters for 'LOCATION', 'IMAGES', 'LICENSE PLATE', and 'STATE'. The 'STATE' filter is expanded, showing a list of states with counts: STATE (0/51), BODY (0/11), MAKE (0/45), COLOR (0/8), IDENTIFIERS (0/4), and RESIDENCY. The main search area shows a date range from 09/06/2023 9:42 AM to 09/26/2023 11:42 AM, with buttons for 'Last 12 hrs', 'Last 24 hrs', 'Last 36 hrs', and 'Last 48 hrs'. A search bar contains the text 'test' and a 'SEARCH NOW' button. The search results are displayed in a grid of eight images, each with a metadata card showing 'Plate', 'Date', 'Location', and 'Source' (AXON).

Search by Device

1. On the Flock search page, select the down arrow next to **Select by**, and then select **Device**. Under **External Sources** select the radio button labeled **Axon Fleet 3**.


The screenshot shows the Axon Search interface with the 'Select by Device' dropdown menu open. The menu options are 'Location', 'Device' (selected), and 'External Sources'. Under 'External Sources', the 'Axon Fleet 3' radio button is selected. The main search area shows a date range from 09/26/2023 1:43 PM to 09/26/2023 3:43 PM, with buttons for 'Last 12 hrs', 'Last 24 hrs', 'Last 36 hrs', and 'Last 48 hrs'. A search bar contains the text 'Search Reason' and a 'SEARCH NOW' button.

2. Adjust the desired time frame and search criteria, enter a **Search Reason**, and then select **Search Now**. Only Axon Fleet 3 results that match the search criteria will be shown. These results will be branded with an Axon logo as the Source.

[back to top](#)

Uploading Evidence from Flock Safety

1. In your Flock account, use the search function to find the read record. In the Flock Search Results, click more options (three dots) and select **Add Evidence**.



The Add to Evidence.com dialog is shown.

2. Assign a User (required) and add a Title (required). You can also add a Case and an ID, but these are optional.
3. Select **Submit Evidence**.

The added evidence can be found in your Evidence list in Axon Evidence or in the applicable Case, if assigned on upload. On the Evidence Detail page, you can see:

1. The Flock camera image with the Flock camera name, location, date, and time of the read in a watermark across the top of the image.
2. The camera metadata, including vehicle and plate details, in the Description field.
3. The map will show the location of the Flock camera.